TCP: Transmission Control Protocol

A Reliable, Connection-Oriented, Byte-Stream Service

OBJECTIVES

This lab is designed to demonstrate the congestion control algorithms implemented by the Transmission Control Protocol (TCP). The lab provides a number of scenarios to simulate these algorithms. You will compare the performance of the algorithms through the analysis of the simulation results.

OVERVIEW

The Internet's TCP guarantees the reliable, in-order delivery of a stream of bytes. It includes a flow-control mechanism for the byte streams that allows the receiver to limit how much data the sender can transmit at a given time. In addition, TCP implements a highly tuned congestion-control mechanism. The idea of this mechanism is to throttle the rate at which TCP sends data, to keep the sender from overloading the network.

The idea of TCP congestion control is for each source to determine how much capacity is available in the network so that it knows how many packets it can safely have in transit. It maintains a state variable for each connection, called the congestion window, which is used by the source to limit how much data the source is allowed to have in transit at a given time. TCP uses a mechanism called additive increase/multiplicative decrease. With this feature, TCP decreases the congestion window when the level of congestion goes up and increases the congestion window when the level of congestion goes down. TCP interprets timeouts as a sign of congestion. Each time a timeout occurs, the source sets the congestion window to half of its previous value. This halving corresponds to the multiplicative decrease part of the mechanism. The congestion window is not allowed to fall below the size of a single packet (the TCP maximum segment size, or MSS). Every time the source successfully sends a congestion window worth of packets, it adds the equivalent of one packet to the congestion window; this is the additive increase part of the mechanism.

TCP uses a mechanism called slow start to increase the congestion window "rapidly" from a cold start in TCP connections. It increases the congestion window exponentially rather than linearly. Finally, TCP utilizes a mechanism called fast retransmit and fast recovery. Fast retransmit is a heuristic that sometimes triggers the retransmission of a dropped packet sooner than the regular timeout mechanism.

In this lab, you will set up a network that utilizes TCP as its end-to-end transmission protocol, and you will analyze the size of the congestion window with different mechanisms.

PRE-LAB ACTIVITIES

- Read Section 5.2 from Computer Networks: A Systems Approach, 5th Edition.
- Go to www.net-seal.net and play the following animations:
 - TCP Connections
 - o TCP Multiplexing
 - o TCP Buffering and Sequencing
 - User Datagram Protocol (UDP)

PROCEDURE


Create a New Project

- **1.** Start **OPNET IT Guru Academic Edition** → Choose **New** from the **File** menu.
- **2.** Select **Project** and click **OK** → Name the project **<your initials>_TCP**, and the scenario **No_Drop** → Click **OK**.
- **3.** In the *Startup Wizard: Initial Topology* dialog box, make sure that **Create Empty Scenario** is selected → Click **Next** → Select **Choose From Maps** from the *Network Scale* list → Click **Next** → Choose **USA** from the Map List → Click **Next** twice → Click **OK**.

Create and Configure the Network

Initialize the network:

- **1.** The *Object Palette* dialog box should now be on the top of your project space. If it is not there, open it by clicking . Make sure that the **internet_toolbox** item is selected from the pull-down menu on the object palette.
- **2.** Add to the project workspace the following objects from the palette: **Application Config**, **Profile Config**, an **ip32 Cloud**, and two subnets.
 - **a.** To add an object from a palette, click its icon in the object palette → Move your mouse to the workspace → Click to drop the object in the desired location → Right-click to finish creating objects of that type.
- **3.** Close the palette.
- 4. Rename the objects you added as shown.
- **5.** Save your project.




100

The ip32_cloud node model represents an IP cloud supporting up to 32 serial line interfaces at a selectable data rate through which IP traffic can be modeled. IP packets arriving on any cloud interface are routed to the appropriate output interface based on their destination IP address. The RIP or OSPF protocol may be used to automatically and dynamically create the cloud's routing tables and select routes in an adaptive manner. This cloud requires a fixed amount of time to route each packet, as determined by the Packet Latency attribute of the node.

Configure the applications:


- **1.** Right-click on the **Applications** node → **Edit Attributes** → Expand the **Application Definitions** attribute and set **rows** to 1 → Expand the new row → Name the row **FTP_Application**.
 - **a.** Expand the **Description** hierarchy → Edit the **FTP** row as shown (first, you will need to set the **Special Value** to **Not Used** while editing the attributes shown):



2. Click OK twice, and Save your project.

Configure the profiles:

- **1.** Right-click on the **Profiles** node → **Edit Attributes** → Expand the **Profile Configuration** attribute and set **rows** to 1.
 - **a.** Name and set the attributes of row 0 as shown \rightarrow Click OK.



The ethernet4_slip8_

represents an IP-based

gateway supporting four Ethernet hub interfaces and eight serial line interfaces.

qtwy node model

Configure the West subnet:

- **1.** Double-click on the **West** subnet node. You get an empty workspace, indicating that the subnet contains no objects.
- **2.** Open the Object palette and make sure that the **internet_toolbox** item is selected from the pull-down menu.
- **3.** Add the following items to the subnet workspace: one **ethernet_server**, one **ethernet4_ slip8_gtwy** router, and connect them with a bidirectional **100_BaseT** link **→ Close** the palette **→ Rename** the objects as shown.

Server_West Router_West

- **4.** Right-click on the **Server_West** node **→ Edit Attributes**:
 - **a.** Edit Application: Supported Services → Set rows to 1 → Set Name to FTP_Application → Click OK.
 - **b.** Edit the value of the Server Address attribute and write down Server West.
 - **c.** Expand the TCP Parameters hierarchy → Set both Fast Retransmit and Fast Recovery to Disabled.
- **5.** Click **OK**, and **Save** your project.

Now, you have completed the configuration of the West subnet. To go back to the top level of the project and click the **Go to next higher level 1** button.

Configure the East subnet:

- **1.** Double-click on the East subnet node. You get an empty workspace, indicating that the subnet contains no objects.
- **2. Open** the Object palette **3** and make sure that the **internet_toolbox** item is selected from the pull-down menu.
- **3.** Add the following items to the subnet workspace: one **ethernet_wkstn**, one **ethernet4_ slip8_gtwy** router, and connect them with a bidirectional **100_BaseT** link → **Close** the palette → Rename the objects as shown.




- **4.** Right-click on the Client_East node → Edit Attributes:
 - **a.** Expand the **Application**: **Supported Profiles** hierarchy → Set rows to 1 → Expand the row 0 hierarchy → Set **Profile Name** to FTP_Profile.
 - **b.** Assign Client_ East to the Client Address attributes.
 - **c.** Edit the Application: Destination Preferences attribute as follows:
 - **d.** Set rows to $1 \rightarrow$ Set Symbolic Name to FTP Server \rightarrow Edit Actual Name \rightarrow Set rows to $1 \rightarrow$ In the new row, assign Server_West to the Name column.
- **5.** Click **OK** three times, and then **Save** your project.

You have now completed the configuration of the **East** subnet. To go back to the project space, click the **Go to next higher level** button.


Connect the subnets to the IP Cloud:

- **1.** Open the Object palette 🖺.
- **2.** Using two PPP_DS3 bidirectional links, connect the East subnet to the IP Cloud and the West subnet to the IP Cloud.
- **3.** A pop-up dialog box will appear, asking you with what to connect the subnet to the IP Cloud with. Make sure to select the **routers.**
- **4.** Close the palette.



Choose the Statistics

- **1.** Right-click on **Server_West** in the **West** subnet, and select **Choose Individual Statistics** from the pop-up menu.
- **2.** In the *Choose Results* dialog box, choose the following statistic:
 - **a.** TCP Connection → Congestion Window Size (bytes) and Sent Segment Sequence Number.



OPNET provides the following capture modes:

All values: This mode collects every data point from a statistic.

Sample: This mode collects the data according to a user-specified time interval or sample count. For example, if the time interval is 10, data is sampled and recorded every 10th second. If the sample count is 10, every 10th data point is recorded. All other data points are discarded.

Bucket: This mode collects all of the points over the time interval or sample count into a "data bucket" and generates a result from each bucket. This is the default mode.

- **b.** Right-click on the Congestion Window Size (bytes) statistic → Choose Change Collection Mode → In the dialog box, check Advanced → From the drop-down menu, assign all values to Capture mode as shown → Click OK.
- **c.** Right-click on the **Sent Segment Sequence Number** statistic → Choose **Change Collection Mode** → In the dialog box, check **Advanced** → From the drop-down menu, assign all values to Capture mode.
- 3. Click OK twice, and Save your project.
- **4.** Click the **Go to next higher level 1** button.

Configure the Simulation

Here we need to configure the duration of the simulation:

- **1.** Click on **3** and the *Configure Simulation* window should appear.
- **2.** Set the duration to 10.0 minutes \rightarrow Click OK.

Duplicate the Scenario

In the network we just created, we assumed a perfect network with no discarded packets. Also, we disabled the fast retransmit and fast recovery techniques in TCP. To analyze the effects of discarded packets and those congestion-control techniques, we will create two additional scenarios.

- **1.** Select **Duplicate Scenario** from the **Scenarios** menu, and give it the name **Drop_NoFast** → Click **OK**.
 - **a.** In the new scenario, right-click on the IP Cloud → Edit Attributes → Assign 0.05% to the Packet Discard Ratio attribute → Click OK, and Save your project.
- **2.** While you are still in the **Drop_NoFast** scenario, select **Duplicate Scenario** from the **Scenarios** menu, and give it the name **Drop_Fast**.
 - **a.** In the Drop_Fast scenario, right-click on Server_ West, which is inside the West subnet → Edit Attributes → Expand the TCP Parameters hierarchy → Enable the Fast Retransmit attribute → Assign Reno to the Fast Recovery attribute.
- **3.** Click **OK**, and **Save** your project.

Run the Simulation

To run the simulation for the three scenarios simultaneously:

- **1.** Go to the Scenarios menu \rightarrow Select Manage Scenarios.
- **2.** Change the values under the **Results** column to **<collect>** (or **<recollect>**) for the three scenarios. Compare with the following figure.
- **3.** Click **OK** to run the three simulations. Depending on the speed of your processor, this task may take several seconds to complete.
- **4.** After the simulation runs complete, click Close \rightarrow Save your project.

View the Results

To view and analyze the results:

- **1.** Switch to the **Drop_NoFast** scenario (the second one) and choose **View Results** from the **Results** menu.
- **2.** Fully expand the **Object Statistics** hierarchy and select the following two results: Congestion Window Size (bytes) and Sent Segment Sequence Number.

104

After fast retransmit sends what appears to be the missing segment, congestion avoidance but not slow start is performed. This is the **fast recovery** algorithm.

With fast retrans-

mit, TCP performs a

to expire.


retransmission of what

appears to be the missing


segment, without waiting for a retransmission timer

The fast retransmit and fast recovery algorithms are usually implemented together (RFC 2001).

To switch to a scenario, choose **Switch to Scenario** from the **Scenarios** menu or just press **Ctrl** + **<scenario number>**.




3. Click **Show**. The resulting graphs should resemble the ones that follow.




4. To zoom in on the details in the graph, click and drag your mouse to draw a rectangle, as shown in the preceding figure.

The graph should be redrawn to resemble the following one:




Notice the **Segment Sequence Number** is almost flat with every drop in the congestion window.

- **5.** Close the *View Results* dialog box and select **Compare Results** from the **Result** menu.
- **6.** Fully expand the **Object Statistics** hierarchy as shown and select the following result: Sent Segment Sequence Number.



7. Click Show. After you zoom in, the resulting graph should resemble the one shown here.



FURTHER READINGS

OPNET TCP Model Description: From the **Protocols** menu, select **TCP** → **Model Usage Guide**.

Transmission Control Protocol: IETF RFC number 793 (www.ietf.org/rfc.html).

EXERCISES

- **1.** Why does the **Segment Sequence Number** remain unchanged (indicated by a horizontal line in the graphs) with every drop in the congestion window?
- **2.** Analyze the graph that compares the **Segment Sequence** numbers of the three scenarios. Why does the **Drop_NoFast** scenario have the slowest growth in sequence numbers?
- **3.** In the Drop_NoFast scenario, obtain the overlaid graph that compares Sent Segment Sequence Number with Received Segment ACK Number for Server_West. Explain the graph. *Hint:* Make sure to assign all values to the Capture mode of the Received Segment ACK Number statistic.
- **4.** Create another scenario as a duplicate of the **Drop_Fast** scenario. Name the new scenario **Q4_Drop_Fast_Buffer**. In the new scenario, edit the attributes of the **Client_East** node and assign 65535 to its **Receiver Buffer (bytes)** attribute (one of the **TCP Parameters**). Generate a graph that shows how the **Congestion Window Size (bytes)** of **Server_West** gets affected by the increase in the receiver buffer. (Compare the congestion window size graph from the **Drop_Fast** scenario with the corresponding graph from the **Q4_Drop_Fast_Buffer** scenario.)

LAB REPORT

Prepare a report that follows the guidelines explained in the Introduction Lab. The report should include the answers to the preceding exercises as well as the graphs you generated from the simulation scenarios. Discuss the results you obtained and compare these results with your expectations. Mention any anomalies or unexplained behaviors.